



Toll-Free Mon - Fri:
888-696-9686 ext.1
International Customers:
707-874-9779
6:00am to 5:00pm p.s.t.

www.mailersmvp.com

Postalsoft Flash Drive Memory Directions

Depending on the type of USB flash drive being used, it is possible that running the DPV and LACSLink directories from the flash drive could improve performance when by-passing Load to Memory. All directories can be installed to the flash drive, or just the DPV and LACSLink files. The below scenario assumes only the DPV and LACSLink files are being run from the flash drive.

Install the DPV and LACSLink directories to the USB flash memory drive by using Postalsoft > Load Directories. This will ensure all the DPV and LACSLink files get copied to the drive.

1. Open the Postalsoft program.
2. Click File > Load Directories... (or click Load Directories from the Start Here pane).
3. Check only DPV and LACSLink
4. On the DPV Directory Loading Options screen, click Downloaded file (.zip).
5. Under Source location, click Browse to locate the ZIP file called US_DPV.ZIP.
6. Under Destination location, click Browse and locate your USB flash memory drive.
7. Click Load.
8. On the LACSLink Directory Loading Options screen, click Downloaded file (.zip).
9. Under Source location, click Browse to locate the ZIP file called US_LACS.ZIP.
10. Under Destination location, click Browse and locate your USB drive.
11. Click Load.
12. Close Postalsoft.

To be sure you are using these directories directly from the USB drive during Address Correction, turn off the Load to Memory option as follows:

1. Open the Postalsoft program.
2. Click Tools > Correct Address > Correction Settings...
3. Click the Multi-Record tab.
4. Under Additional USPS Processing Options, uncheck Load to memory.
5. Click OK.

If manually copying the DPV and LACSLink directories to the flash drive and not using the Load Directories, you will also need to make sure the following files are moved to the flash drive as well in order for DPV and LACSLink processing to work:

1. Open My Computer.
2. Browse to where Postalsoft is installed. By default, Postalsoft is installed under C:\Postalsoft\ (or C:\Firstlogic\Postalssoft\)
3. Open the DPV folder.
4. Copy dpvw.txt, dpvx.txt, dpvy.dpv, and dpvz.dpv.
5. Paste these DPV files to where the DPV directories are located on the USB drive.
6. Browse to where Postalsoft is installed.
7. Open the LACSLink folder.
8. Copy lacsw.txt, lacsx.txt, lacsy.ll, and lacsz.ll.
9. Paste these LACSLink files to where the LACSLink directories are located on the USB drive.